

Humidex Rating and Work Fact Sheet



WHAT IS HUMIDEX?

Humidex is a measure of how hot we feel. It is a parameter intended for the general public to express how the combined effects of warm temperatures and humidity are perceived. It provides a number that describes how hot people feel, much in the same way the equivalent chill temperature, or “wind chill factor,” describes how cold people feel.

Environment Canada uses humidex ratings to inform the general public when conditions of heat and humidity are possibly uncomfortable.

Table 1	
Humidex Range	Degree of Comfort
20-29	comfortable
30-39	some discomfort
40-45	great discomfort; avoid exertion
above 45	dangerous; heat stroke possible

What is the importance of humidity?

The body attempts to maintain a constant internal temperature of 37°C at all times. In hot weather, the body produces sweat, which cools the body as it evaporates. As the humidity or the moisture content in the air increases, sweat does not evaporate as readily. Sweat evaporation stops entirely when the relative humidity reaches about 90 percent. Under these circumstances, the body temperature rises and may cause illness.

What are some of the hazards of working in hot environments?

There are several common heat-related illnesses. Some are more severe than others.

Heat rash, or prickly heat, occurs when blocked sweat glands become inflamed. This painful rash reduces the body’s ability to sweat and to tolerate heat.

Heat cramps are painful spasms of the muscles. The muscles used in doing the work are most susceptible. The spasms are caused by the failure of the body to replace its lost body salts and usually occur after heavy sweating.

Heat exhaustion results when the body loses large amounts of fluid by sweating during work in hot environments. The skin becomes cool and clammy. Symptoms include profuse sweating, weakness, dizziness, nausea, and headaches.

Heat stroke is the most serious condition and requires immediate medical attention. The body temperature becomes very high (even exceeding 41°C). Complete or partial loss of consciousness is possible. Sweating is not a good symptom of heat stress as there are two types of heat stroke – “classical” where there is little or no sweating (usually occurs in children, persons who are chronically ill, and the elderly), and “exertional” where body temperature rises because of strenuous exercise or work and sweating is usually present.

Can workplaces use humidex to monitor conditions that may result in heat-related illness?

Humidex as reported by weather forecasters is intended for the general public to express the combined effects of warm temperatures and humidity.

Heat-related illnesses depend on many workplace factors in addition to air temperature and humidity. Wind speed or air movement, work load, radiant heat sources and a person’s physical condition are also important.

Under certain workplace conditions, the humidex may serve as an indicator of discomfort resulting from occupational exposures to heat.

For example, when humidity is high, but when work load, wind speed and radiant heat sources do not significantly contribute to the heat burden, humidex may be useful. Offices are typical of workplaces where humidex could be used. It is important to use the values of the temperature and relative humidity obtained by actual measurements taken in the workplace. Conditions inside the workplace may significantly differ from those given by the Weather Service.

How do I know what the humidex is?

If you know the temperature and relative humidity, the following chart can be used to determine the humidex rating. For example, if the temperature is 30°C and the relative humidity is 70%, the humidex rating is 41. This level is considered a level of “great discomfort” and exertion should be avoided.

If working outdoors is an absolute necessity, drink plenty of liquids and take frequent rest breaks. In hot, humid conditions, there is a considerable risk of heat stroke and sunstroke.”

How is humidex interpreted?

The relation between humidex and comfort is subjective. It varies widely between individuals.

Workplaces must use caution when applying the humidex rating. A high humidex rating can serve as a cue to assess workplace conditions more precisely.

The Occupational Health Clinics for Ontario Workers Inc. (OHCOW) created a humidex-based response plan that translated the TLVs® WBGTs into humidex values and developed

recommended responses for each humidex range. This plan was developed as a tool to help workplaces as most find using the WBGT complicated and expensive.

While technically there is no way to directly compare WBGT and humidex values, this humidex response plan provides an additional guideline that uses information that is easily available to most employers. OHCOW notes, “in the translation process some simplifications and assumptions have been made, therefore, the plan may not be applicable in all circumstances and/or workplaces (follow steps 1 through 5 to ensure

the humidex plan is appropriate for your workplace“

See Table 2 for details.

Notes: These humidex levels are for unacclimatized workers performing moderate physical activity. The ACGIH specifies an action limit and a TLV® to prevent workers' body temperature from exceeding 38°C (38.5°C for acclimatized workers). Below the action limit (Humidex 1 for work of moderate physical activity) most workers will not experience heat stress. Most healthy, well-hydrated, acclimatized workers not on medications will be able to tolerate heat stress up to the TLV®. (Humidex 2 for moderate physical activity). Between Humidex 1 and Humidex 2, general heat stress controls are needed and above Humidex 2 job-specific controls are needed.

Table 2

Recommended Actions Based on the Humidex Reading

Humidex 1 – Moderate physical work, unacclimatized worker, OR Heavy physical work, acclimatized worker	Response	Humidex 2 – Moderate physical work, acclimatized worker, OR Light physical work, unacclimatized worker
25 - 29	• supply water to workers on an "as needed" basis	32 - 35
30 - 33	• post Heat Stress Alert notice • encourage workers to drink extra water • start recording hourly temperature and relative humidity	36 - 39
34 - 37	• post Heat Stress Warning notice • notify workers that they need to drink extra water • ensure workers are trained to recognize symptoms	40 - 42
38 - 39	• work with 15 minutes relief per hour can continue • provide adequate cool (10 - 15°C) water • at least 1 cup (240 mL) of water every 20 minutes • workers with symptoms should seek medical attention	43 - 44
40 - 41	• work with 30 minutes relief per hour can continue in addition to the provisions listed previously	45 - 46*
42 - 44	• if feasible, work with 45 minutes relief per hour can continue in addition to the provisions listed above	47 - 49
45 or over	• only medically supervised work can continue	50* and over

Source: Occupational Health Clinics for Ontario Workers (OHCOW) – "Humidex Based Heat Response Plan"

IMPORTANT: Consult with the OHCOW material for interpretation and use of this chart. ALWAYS follow steps 1 to 5 as listed on the OHCOW web site. Also see the Humidex-based Heat Stress Calculator.